

Advanced Properties

Use the Advanced tab to configure the conversion options, specify the size of a quiz and edit settings to control Flash and HTML5 quiz playback.

The screenshot shows the 'Publish Quiz' dialog box in iSpring QuizMaker. The 'Advanced' tab is selected. On the left, there are three output format options: 'Web' (selected), 'iSpring Learn', 'LMS', and 'Word'. The 'Content Properties' section includes a 'Fit to window' checkbox (unchecked), 'Size' fields set to 720 x 540 pixels, and a 'Scale' field set to 100%. The 'HTML5 Properties' section has a checked 'Extended audio and video compatibility' option. The 'Flash Movie Properties' section includes a 'Flash Movie Control' header, 'Flash version' set to 'Flash 10', 'Frame rate' set to 24, and checked options for 'Disable Flash menu' and 'Disable "Print" option'. The 'Playback Options' section has 'On restart' set to 'Prompt to resume'. 'Publish' and 'Cancel' buttons are at the bottom right.

Content Properties	
Fit to window	Scales the quiz up to fit the entire screen area of your browser.
Size	Width and height of the output quiz.
Scale	Percentage of the published quiz size relative to the original quiz size.

HTML5 Properties	
Extended audio and video compatibility	Check this option to turn on audio and video compatibility with Firefox and Opera browsers. If this option is checked, iSpring QuizMaker will generate additional audio and video files for Firefox and Opera browsers. Note: Enabling this option will increase the final size of the HTML5 quiz.

Flash Movie Properties	
Flash version	Select the Flash Player version.
Frame rate	The number of Flash frames per second. Low FPS is not recommended, because this can cause flickering in animations.
Disable Flash menu	Disables the right-click menu and top menu in a generated Flash movie window.

Disable "Print" option	Select this option if you don't want to allow the printing of your output Flash quiz. 'Print' option in the right-click menu will be disabled in the generated Flash file.
-------------------------------	--

Playback Options	
On restart	<p>Set up the playback of the quiz when reopened.</p> <p>Prompt to resume – When reopening the quiz, the user will be able to choose from two options: either to continue the previous session or play the quiz from the beginning.</p> <p>Always resume – The quiz is always resumed from where it has been interrupted without user's intention.</p> <p>Always start over – The quiz is always played from the beginning.</p>

 HTML5 Properties are disabled if you publish your presentation to Flash. Flash Movie Properties are disabled when publishing Presentation to HTML5.

blocked URL