

Adding and Deleting Questions


You can add unlimited number of questions to a quiz using 11 different categories of graded questions and 12 non-graded question categories.

- [Adding Questions](#)
- [Deleting Questions](#)

Adding Questions

To add a question to your quiz:

1. Select one of the question types in the **Graded Questions** or **Survey Questions** drop-down menus.



2. Type your question in the **Question** field.

[blocked URL](#)

3. Customize question text style (Bold/Italic/Underline) and [add media resources](#) to it.
4. Add one or several choices to your question in the Answer/Details area.
In addition, you can maximize the **Answers** area to have more space while working with long descriptions or large images. Once panel is maximized, you can simply restore its original size to see question details by clicking the **Restore** button in the upper left corner of the panel.

[blocked URL](#)

5. In the **Options** area, uncheck the Use default options checkbox and change defaults if necessary.

[blocked URL](#)

Option	Description
--------	-------------

Use default option	Uncheck the Use default options checkbox to override the Question Defaults settings . Select this checkbox to apply default settings (1 attempt; 10 points awarded for each correct answer; shuffled answers; partial answer - not allowed).
Score	Choose whether the score and penalties will be awarded by question or by answer.
Points	Specify the number of points given for a correct answer. If the score is given by answer, you can set custom score per each answer choice for two question categories: Multiple Choice and Multiple Response .
Penalties	Specify the number of penalty points given for an incorrect answer. If the penalty is applied by answer, you can set custom penalty points per each answer choice for two question categories: Multiple Choice and Multiple Response . Note: Penalty point for each answer should start with the minus sign.
Attempts	Specify the number of question attempts available.
Shuffle answers	Select this checkbox to show answers in the shuffled order.
Allow partial answer	Select this checkbox to treat partial answers as correct ones. Note: You cannot set penalties if partial answer is allowed. The Penalty field is disabled if you select Allow partial answer .
May skip	This option is available for survey questions only. If you select this option, survey participants will be able to skip the question without answering it.
Limit time to answer the questions	Set the allowed time to answer a question. After the time runs out, the question will be automatically submitted with the selected answer.
Answers are case sensitive	Enabling this option makes the input text case sensitive.
Limit number of answers	This option is available for Multiple Response and Pick Many questions only. Specify the maximum number of answers, which user can give to this question.

6. If necessary, [change feedback settings](#) for the question.
7. Enable [branching](#) if you want to control the order of questions in quizzes depending on the students' answers.

Deleting Questions

1. Select a question in the list on the left side of the QuizMaker window.
2. Right-click the selected question and choose **Delete** in the context menu
or
Press **Delete** on your keyboard.
3. Click **Yes** in the confirmation dialog.

Note: You can select several questions by holding down the **CTRL** or **SHIFT** keyboard key while you click questions with the mouse.
[blocked URL](#)