Upgrading from a Business to a Concurrent License

To upgrade from your Business license to a Concurrent license, follow the steps below:

- 1. Install the new product without uninstalling the old one. You can use this video instruction to install iSpring Suite.
- If your product verion is 8.3.1 or higher, a fresh installation is not necessary. You can check your version in the About window.
- 2. Open iSpring Suite and click **About** on the toolbar.



3. In the About window, click Change License Key.

i	About	×
*	Sispring Suite Version 8.5.1 Build 17969	
2 2 2	Irina Test Business License K6N0K-4GS04-XXXXX-XXXXX-XXXXX-XXXXX-XXXXX-351QJ-NWHAR Change License Key Maintenance is active	
	Buy Maintenance Renewal Activate Maintenance Renewal	
<u>Get techni</u> Copyright	cal support © 2005-2017 iSpring Solutions, Inc. All rights reserved. <u>Additional Copyright Information</u>	

4. The Activation Wizard window will pop up. Keep the checkbox 'Enter another license key' selected and click Next.

iSpring Suite Activation Wizard						
License Activation Settings Select one of the options below to manage license activations						
Enter another license key or registration info						
Choose this option if you want to activate your product copy using a different license key or change the registration info.						
O Deactivate the license Your license will be deactivated, and you will be able to activate iSpring Suite on another computer.						
< Back Next > Cancel Help						

5. Insert the concurrent license key and click Next. Use the same key that you specified for the License Server activation.

*	iSpring Suite Activation Wizard ×							
Enter Lic Copy	ense Key and paste the license key you received after purchasing your iSpring license							
Paste your li	Paste your license key to activate iSpring Suite:							
XXXXX-XXXX	XXXXX-XXXXX-XXXXX-XXXXX-XXXXX-XXXXX-XXXX							
	Don't have a license key? Purchase Online							
	< Back Next > Cancel Help							

6. Specify the computer name where the License Server is installed. If both client and server parts are installed on one and the same computer, then type in 'localhost'.

*	iSpring Suite	Activation \	Vizard	×
Enter Server Name Enter server nam	e and Port e and port to connect	to the license se	rver	\sim
You have entered a key	which requires a conn	ection to the lice	nse server.	
Name of computer on ye	our network with licens	e server:		
localhost				
Use port:				
9979				
	< <u>B</u> ack	<u>N</u> ext >	Cancel	Help

7. In the 'Use port' field, specify the same port that you indicated in the Server License Management Console. The default value is 9979. Click Next.

* iSpring Suite Activation Wizard	×
Enter Server Name and Port Enter server name and port to connect to the license server	\sim
You have entered a key which requires a connection to the license server.	
localhost	
Use port:	
9979	
< Back Next > Cancel	Help

Your product is now activated. You can start using the iSpring product if there are any available connections (floating licenses) on the server.